

2. Image reading and display

2.1. Reading of images:

`img = cv2.imread('yahboom.jpg', 0)` The first parameter is the path of the image, and the second parameter is how to read the image.

`cv2.IMREAD_UNCHANGED`: Keep the original format unchanged, -1;

`cv2.IMREAD_GRAYSCALE`: Read the image in grayscale mode, which can be represented by 0;

`cv2.IMREAD_COLOR`: , read a color picture, which can be represented by 1; default value

`cv2.IMREAD_UNCHANGED`: Read in an image and include its alpha channel, which can be represented by 2.

2.2. Image display

`cv.imshow('frame', frame)`: Open a window named frame and display frame data (image/video data)

Parameter meaning:

The first parameter represents the name of the window that is created and opened.

The second parameter represents the image to be displayed

2.2.1. Code and actual effect display

Code path:

```
/home/jetson/Dofbot/4.opencv_EN/1.OpenCV_Getting_started/01_OpenCV_image_read_display.ipynb
```

Main code:

```
import cv2
img = cv2.imread('yahboom.jpg', 1)
# cv2.imshow('image', img) #This line can only be executed from the py file on
the command line, and a video window will pop up.
# cv2.waitKey (0)
```

```
#bgr8 to jpeg format
import enum
import cv2
def bgr8_to_jpeg(value, quality=75):
    return bytes(cv2.imencode('.jpg', value)[1])
```

```
# The image component in jupyterLab displays the read image
import ipywidgets.widgets as widgets
image_widget = widgets.Image(format='jpg', width=800, height=800)
display(image_widget)
image_widget.value = bgr8_to_jpeg(img)
```

After running the code block, you can see the following interface, and the image has been read out.

